

Installing/Updating the “Biometric” Middleware

The Biometric Middleware (BMW) is running as a windows service.


If BMW is installed **fresh** on a **new** machine it must be first installed as Service.

Please follow the steps below to install BMW fresh as service:

Use the whole content of the ZIP file (BiometricServer x.x.zip) for installation

- Copy the entire content of the ZIP file to any *arbitrary* folder e.g. C:\Biometric without the “Release” pathname
- Run cmd.exe as administrator !
- Navigate the console to C:\Biometric (or any other you have chosen)
- Run the command: BiometricServer.exe install
- Run the command: BiometricServer.exe start


The BMW application is now running as service and you can apply the usual service tasks like Start/Stop/....



To **remove** (uninstall) the service simple call ***BiometricServer.exe uninstall*** from within the folder the exe resides.

Updating an existing Biometric installation:

- Stop the running service



- Copy the file "***BiometricServer.exe.config***" to a save place (we need it later)
- Copy the entire content of the ZIP file (without the "Release" pathname) to the folder where the current installation exists, overwriting all former files.
- Copy the **saved** "***BiometricServer.exe.config***" back to its original location.
- Start again the service.

Hint: the "config" file contains important settings (e.g IP addresses, logger path,) and should therefore not be overwritten by the config file which comes with the new ZIP archive.